

PureConnect®

2018 R5

Generated:

12-November-2018

Content last updated:

16-March-2018

See Change Log for summary of changes.

<mark>e</mark>genesys™

Status Aggregator

Technical Reference

Abstract

This technical reference shows how to install and configure Status Aggregator.

For the latest version of this document, see the PureConnect Documentation Library at: http://help.genesys.com/cic.

For copyright and trademark information, see https://help.genesys.com/cic/desktop/copyright_and_trademark_information.htm.

Table of Contents

Introduction to Status Aggregator3CIC Clients4What Is a Status?5What Status Aggregator Does7How Status Aggregator Does7How Status Aggregator Works8How Status Aggregator Works with Different CIC Editions10How Status Aggregator Uses Security Certificates11Installing and Configuring Status Aggregator12Installation Pre-Requisites and System Requirements12Install Status Aggregator Contact List Sources13Overview of Configuring Status Aggregator152. Configure Status Aggregator Contact List Sources173. Import Certificates Into Each CIC Server184. Set Parameters for the Status Aggregator20Start Status Aggregator20Start Status Aggregator20Start Status Aggregator21Add Status Aggregator21Add Status Aggregator Data Bit Practices21Add Status Aggregator20Start Status Aggregator Contact List Sources21Add Status Aggregator20Start Status Aggregator20Start Status Aggregator21Add Status Aggregator Data Bit Practices21Add Status Aggregator21Appendix A: Antivirus Requirements and Best Practices22Change Log23Copyright and Trademark Information24	Table of Contents	2
What Is a Status?5What Status Aggregator Is6What Status Aggregator Does7How Status Aggregator Works8How Status Aggregator Uffers from Multi-Site9How Status Aggregator Uses Security Certificates11Installing and Configuring Status Aggregator12Installation Pre-Requisites and System Requirements12Install Status Aggregator13Generate SSL Security Certificates13Overview of Configuring Status Aggregator151: Configure Status Aggregator Data Sources162: Configure Status Aggregator Contact List Sources173: Import Certificates Into Each CIC Server184: Set Parameters for the Status Aggregator20Start Status Aggregator20Start Status Aggregator20Start Status Aggregator21Add Status Aggregator21Add Status Aggregator Directory to the CIC Clients21Appendix A: Antivirus Requirements and Best Practices22Change Log23	Introduction to Status Aggregator	3
What Status Aggregator Is6What Status Aggregator Does7How Status Aggregator Works8How Status Aggregator Works with Different CIC Editions9How Status Aggregator Works with Different CIC Editions10How Status Aggregator Uses Security Certificates11Installing and Configuring Status Aggregator12Installation Pre-Requisites and System Requirements12Install Status Aggregator Data Sources13Overview of Configuring Status Aggregator151: Configure Status Aggregator Data Sources162: Configure Status Aggregator Contact List Sources173: Import Certificates Into Each CIC Server184: Set Parameters for the Status Aggregator20Start Status Aggregator20Start Status Aggregator20User Operation of Status Aggregator21Add Status Aggregator Directory to the CIC Clients21Appendix A: Antivirus Requirements and Best Practices22Change Log23	CIC Clients	4
What Status Aggregator Does7How Status Aggregator Works8How Status Aggregator Differs from Multi-Site9How Status Aggregator Works with Different CIC Editions10How Status Aggregator Uses Security Certificates11Installing and Configuring Status Aggregator12Installation Pre-Requisites and System Requirements12Install Status Aggregator13Generate SSL Security Certificates13Overview of Configuring Status Aggregator151: Configure Status Aggregator Data Sources162: Configure Status Aggregator Contact List Sources173: Import Certificates Into Each CIC Server184: Set Parameters for the Status Aggregator20Start Status Aggregator20User Operation of Status Aggregator21Add Status Aggregator Directory to the CIC Clients21Appendix A: Antivirus Requirements and Best Practices22Change Log23	What Is a Status?	5
How Status Aggregator Works8How Status Aggregator Differs from Multi-Site9How Status Aggregator Works with Different CIC Editions10How Status Aggregator Uses Security Certificates11Installing and Configuring Status Aggregator12Installation Pre-Requisites and System Requirements12Install Status Aggregator13Generate SSL Security Certificates13Overview of Configuring Status Aggregator13Overview of Configuring Status Aggregator151: Configure Status Aggregator Data Sources162: Configure Status Aggregator Contact List Sources173: Import Certificates Into Each CIC Server184: Set Parameters for the Status Aggregator20Start Status Aggregator20Start Status Aggregator20User Operation of Status Aggregator21Add Status Aggregator Directory to the CIC Clients21Appendix A: Antivirus Requirements and Best Practices22Change Log23	What Status Aggregator Is	6
How Status Aggregator Differs from Multi-Site9How Status Aggregator Works with Different CIC Editions10How Status Aggregator Uses Security Certificates11Installing and Configuring Status Aggregator12Installation Pre-Requisites and System Requirements12Install Status Aggregator13Generate SSL Security Certificates13Overview of Configuring Status Aggregator151: Configure Status Aggregator Data Sources162: Configure Status Aggregator Contact List Sources173: Import Certificates Into Each CIC Server184: Set Parameters for the Status Aggregator Server19Starting and Running Status Aggregator20User Operation of Status Aggregator20User Operation of Status Aggregator21Add Status Aggregator Directory to the CIC Clients21Appendix A: Antivirus Requirements and Best Practices22Change Log23	What Status Aggregator Does	7
How Status Aggregator Works with Different CIC Editions10How Status Aggregator Uses Security Certificates11Installing and Configuring Status Aggregator12Installation Pre-Requisites and System Requirements12Install Status Aggregator13Generate SSL Security Certificates13Overview of Configuring Status Aggregator151: Configure Status Aggregator Data Sources162: Configure Status Aggregator Contact List Sources173: Import Certificates Into Each CIC Server184: Set Parameters for the Status Aggregator20Start Status Aggregator20Start Status Aggregator21Add Status Aggregator Directory to the CIC Clients21Appendix A: Antivirus Requirements and Best Practices22Change Log23	How Status Aggregator Works	8
How Status Aggregator Uses Security Certificates11Installing and Configuring Status Aggregator12Installation Pre-Requisites and System Requirements12Install Status Aggregator13Generate SSL Security Certificates13Overview of Configuring Status Aggregator151: Configure Status Aggregator Data Sources162: Configure Status Aggregator Contact List Sources173: Import Certificates Into Each CIC Server184: Set Parameters for the Status Aggregator Server19Starting and Running Status Aggregator20User Operation of Status Aggregator21Add Status Aggregator Directory to the CIC Clients21Appendix A: Antivirus Requirements and Best Practices22Change Log23	How Status Aggregator Differs from Multi-Site	9
Installing and Configuring Status Aggregator12Installation Pre-Requisites and System Requirements12Install Status Aggregator13Generate SSL Security Certificates13Overview of Configuring Status Aggregator151: Configure Status Aggregator Data Sources162: Configure Status Aggregator Contact List Sources173: Import Certificates Into Each CIC Server184: Set Parameters for the Status Aggregator20Starting and Running Status Aggregator20User Operation of Status Aggregator21Add Status Aggregator Directory to the CIC Clients21Appendix A: Antivirus Requirements and Best Practices22Change Log23	How Status Aggregator Works with Different CIC Editions	10
Installation Pre-Requisites and System Requirements12Install Status Aggregator13Generate SSL Security Certificates13Overview of Configuring Status Aggregator151: Configure Status Aggregator Data Sources162: Configure Status Aggregator Contact List Sources173: Import Certificates Into Each CIC Server184: Set Parameters for the Status Aggregator19Starting and Running Status Aggregator20Start Status Aggregator20User Operation of Status Aggregator21Add Status Aggregator Directory to the CIC Clients21Appendix A: Antivirus Requirements and Best Practices22Change Log23	How Status Aggregator Uses Security Certificates	11
Install Status Aggregator13Generate SSL Security Certificates13Overview of Configuring Status Aggregator151: Configure Status Aggregator Data Sources162: Configure Status Aggregator Contact List Sources173: Import Certificates Into Each CIC Server184: Set Parameters for the Status Aggregator Server19Starting and Running Status Aggregator20Start Status Aggregator20User Operation of Status Aggregator21Add Status Aggregator Directory to the CIC Clients21Appendix A: Antivirus Requirements and Best Practices22Change Log23	Installing and Configuring Status Aggregator	12
Generate SSL Security Certificates13Overview of Configuring Status Aggregator151: Configure Status Aggregator Data Sources162: Configure Status Aggregator Contact List Sources173: Import Certificates Into Each CIC Server184: Set Parameters for the Status Aggregator Server19Starting and Running Status Aggregator20Start Status Aggregator20User Operation of Status Aggregator21Add Status Aggregator Directory to the CIC Clients21Appendix A: Antivirus Requirements and Best Practices22Change Log23	Installation Pre-Requisites and System Requirements	12
Overview of Configuring Status Aggregator151: Configure Status Aggregator Data Sources162: Configure Status Aggregator Contact List Sources173: Import Certificates Into Each CIC Server184: Set Parameters for the Status Aggregator Server19Starting and Running Status Aggregator20Start Status Aggregator20User Operation of Status Aggregator21Add Status Aggregator Directory to the CIC Clients21Appendix A: Antivirus Requirements and Best Practices22Change Log23	Install Status Aggregator	13
1: Configure Status Aggregator Data Sources162: Configure Status Aggregator Contact List Sources173: Import Certificates Into Each CIC Server184: Set Parameters for the Status Aggregator Server19Starting and Running Status Aggregator20Start Status Aggregator20User Operation of Status Aggregator21Add Status Aggregator Directory to the CIC Clients21Appendix A: Antivirus Requirements and Best Practices22Change Log23	Generate SSL Security Certificates	13
2: Configure Status Aggregator Contact List Sources173: Import Certificates Into Each CIC Server184: Set Parameters for the Status Aggregator Server19Starting and Running Status Aggregator20Start Status Aggregator20User Operation of Status Aggregator21Add Status Aggregator Directory to the CIC Clients21Appendix A: Antivirus Requirements and Best Practices22Change Log23		15
3: Import Certificates Into Each CIC Server184: Set Parameters for the Status Aggregator Server19Starting and Running Status Aggregator20Start Status Aggregator20User Operation of Status Aggregator21Add Status Aggregator Directory to the CIC Clients21Appendix A: Antivirus Requirements and Best Practices22Change Log23		
4: Set Parameters for the Status Aggregator Server19Starting and Running Status Aggregator20Start Status Aggregator20User Operation of Status Aggregator21Add Status Aggregator Directory to the CIC Clients21Appendix A: Antivirus Requirements and Best Practices22Change Log23		
Starting and Running Status Aggregator20Start Status Aggregator20User Operation of Status Aggregator21Add Status Aggregator Directory to the CIC Clients21Appendix A: Antivirus Requirements and Best Practices22Change Log23		
Start Status Aggregator20User Operation of Status Aggregator21Add Status Aggregator Directory to the CIC Clients21Appendix A: Antivirus Requirements and Best Practices22Change Log23	· · · · · · · · · · · · · · · · · · ·	
User Operation of Status Aggregator21Add Status Aggregator Directory to the CIC Clients21Appendix A: Antivirus Requirements and Best Practices22Change Log23		
Add Status Aggregator Directory to the CIC Clients21Appendix A: Antivirus Requirements and Best Practices22Change Log23		
Appendix A: Antivirus Requirements and Best Practices22Change Log23		
Change Log 23		
	Appendix A: Antivirus Requirements and Best Practices	22
Copyright and Trademark Information 24	Change Log	23
	Copyright and Trademark Information	24

Introduction to Status Aggregator

This content is for system administrators and others who want to:

- Understand the purpose, concepts, and architecture of the Status Aggregator.
- Install and configure Status Aggregator on the Status Aggregator server.
- Configure Interaction Administrator to work with Status Aggregator.
- Import Status Aggregator security certificates into each CIC server.
- Learn how to configure CIC clients to work with Status Aggregator.

CIC Clients

Customer Interaction Center (CIC) supports two interaction management client applications. This documentation uses the term "CIC client" to refer to either Interaction Connect or Interaction Desktop.

What Is a Status?

Status Aggregator consolidates status information about CIC users. That information has three components:

Status key

This key is a string value (Figure 1, a) that can be mapped to various attributes (b) specified in Interaction Administrator. It can correspond to a persistent status value (such as "Gone Home" or "On Vacation") or a non-persistent value (such as "Follow Up"). Persistent values are expected to survive across a server restart or user logout; non-persistent values are not. The status key may be accompanied by per-instance data, such as "Until" data indicating when the user expects to exit the status or a status detail string that can be displayed along with the user's status.

"On Phone" indication

The "On Phone" indication is a Boolean value, which indicates whether the user has any active interactions on his or her user queue. If the user is logged into a station, this also includes interactions on his or her station queue.

CIC logon indication

The CIC logon indicator is a string value. If empty, it indicates that the user is not currently logged in to a CIC server. If nonempty, it specifies the name of the CIC server where the user resides.

These status values are displayed in various user-side displays and are also used by various CIC subsystems (such as AcdServer). They are also used to implement the "Camp" feature that starts a call when a camped-on user changes his/her status.

Eile Edit ⊻iew ⊆ontext Window Help									
i 🖬 📄 🖹 🥔 🌱 📊	<u>a</u>								
🗉 🖳 Stations 📃	Message Name 🛛 🛆	Message	Group	User Seleccapie	Persistent	DND	Date	Time	ACD
😥 💯 Managed IP Phones	AcdAgentNotAnswering	ACD - Agent Not Answering	UNAVAILABLE	No	No	Yes	No	No	No
👲 Audio Sources	At a training session	At a Training Session	TRAINING	Yes	Yes	Yes	Yes	Yes	No
Server Parameters	At Customer Site	At Customer Site	UNAVAILABLE	Yes	Yes	Yes	Yes	Yes	No /
Structured Parameters	At Lunch	At Lunch	BREAK	Yes	Yes	Yes	No	Yes	No/
	At Play	At Play	BREAK	Yes	Yes	Yes	No	No	Nç
	Available	Available	AVAILABLE	Yes	Yes	No	No	No	Y.
	Available, Callback	Available, Callback	AVAILABLE	Yes	No	No	No	No	- N
🛛 🥵 People	Available, Follow-Me	Available, Follow-Me	AVAILABLE	Yes	Yes	No	Yes	Yes	
- 🔊 Default User	Available, Forward	Available, Forward	AVAILABLE	Yes	Yes	No	No	No	
	Available, No ACD	Available, No ACD	AVAILABLE	Yes	Yes	No	No	No	
- 🚨 Users	Available, Researching	Available, Researching	AVAILABLE	No	Yes	No	No	Yes	
- Sa Workgroups	Available, WAH	Available, WAH	AVAILABLE	Yes	Yes	No	No	No	
Assword Policies	Awaiting Callback	Awaiting Callback	UNAVAILABLE	No	Yes	Yes	No	Yes	Ň
	Away from desk	Away from desk	UNAVAILABLE	Yes	Yes	Yes	No	No	Nk.
Land I	Bank Holiday	Bank Holiday	UNAVAILABLE	Yes	Yes	Yes	Yes	No	No
🕅 Skills	Campaign Call		AVAILABLE	No	Yes	No	No	Yes	Yes
😟 🥼 Account Codes	Code Red	Code Red	UNAVAILABLE	Yes	No	No	No	No	No
	Do Not disturb	Do Not Disturb	UNAVAILABLE	Yes	Yes	Yes	No	No	No
Client Buttons	Do Not Disturb, awaiting call	Do Not Disturb, awaiting call	AVAILABLE	Yes	No	No	No	Yes	No
🗉 🐗 Client Configuration	Follow Up	Follow Up	FOLLOWUP	No	No	Yes	No	No	No
System Configuration	Gone Home	Gone Home	UNAVAILABLE	Yes	Yes	Yes	No	No	No
	In a meeting	In a Meeting	UNAVAILABLE	Yes	Yes	Yes	Yes	Yes	No
Interaction Processor	In the Shower	In the shower	UNAVAILABLE	Yes	Yes	Yes	No	No	No
Phone Numbers	Medical Appointment	Medical Appointment	UNAVAILABLE	Yes	Yes	Yes	Yes	Yes	No
	On a Conference Call	On a Conference Call	UNAVAILABLE	Yes	Yes	Yes	No	Yes	No /
	On Break	On Break	BREAK	Yes	Yes	Yes	No	No	No
Reports	On Other Call	On Other Call	AVAILABLE	Yes	Yes	Yes	No	Yes	Ne
System Parameters	On Vacation	On Vacation	UNAVAILABLE	Yes	Yes	Yes	Yes	No	N
- ·	Out of the office	Out of the Office	UNAVAILABLE	Yes	Yes	Yes	Yes	Yes	- E
	Out of town	Out of Town	UNAVAILABLE	Yes	Yes	Yes	Yes	Yes	
	Remote Site	South Florida Employee	UNAVAILABLE	Yes	Yes	Yes	No	No	
	Researching	Researching	FOLLOWUP	Yes	Yes	No	No	No	
🔁 Mail	Sick at home	Sick at Home	UNAVAILABLE	Yes	Yes	Yes	No	No	
🗉 🚵 Fax	Station Not Available	Station Not Available	UNAVAILABLE	No	No	Yes	No	No	1
IC Data Sources	Support Call Back	Support Call Back	FOLLOWUP	Yes	No	No	No	No	N
in Data boarces	Support Callback	Support Callback	FOULT		No	No	No	No	No
	Morking at Home	Working At Home			Ves	Yes	No	No	N.


What Status Aggregator Is

Status Aggregator is a software subsystem that works with Customer Interaction Center. Status Aggregator allows users of the CIC clients to see the status not only of people in their own offices, but also in any remote office whose Customer Interaction Center server shares information with the Status Aggregator server.

Status Aggregator is intended for large organizations that have too many users to host on a single CIC server. Such organizations often have multiple sites and want to monitor employee or user status regardless of location. Status Aggregator makes users' status visible to all CIC servers that are connected to the Status Aggregator server.

What Status Aggregator Does

Status Aggregator runs on a dedicated server. It consolidates status information about users residing on multiple CIC servers, whether in the same or in geographically separate offices. In turn, the Status Aggregator server makes this consolidated information available to all of the CIC servers.



Consolidated information flows from Status Aggregator to CIC servers to users.

The diagram shows a simplified example. In the diagram, each CIC server knows about its own users. CIC server 1, for example, knows about users 1–1,000. From the Active Directory server, CIC server 1 learns that users 1,001–2,000 are on some other CIC server, but does not have status information about those users. CIC server 1 can then go to the Status Aggregator server to obtain status information about those users if it is available. Users of CIC server 1 can then view status information about users who are logged in to CIC server 2.

Using a separate, dedicated Status Aggregator server solves the scalability problem that occurs when an organization has too many users to host on a single CIC server. When an organization wants to consolidate information about users from multiple CIC servers, the Status Aggregator server can scale up to the load and provide status information in real time.

Status Aggregator can work on a single Status Aggregator server or on multiple Status Aggregator servers to provide mirroring and fault tolerance. A single Status Aggregator server (or a single Status Aggregator server with a mirror server to provide nonstop operation if there is a problem) can:

- Efficiently handle up to five CIC servers.
- Efficiently handle up to 50,000 CIC users.

How Status Aggregator Works

The Status Aggregator server:

- Receives notifications of user status changes and caches them.
- Receives queries for status values from client CIC servers.
- Receives and manages requests to monitor for changes in the status of specific users.

The server does not try to map from one status type to another and does not proactively request status values from other CIC servers. It is by design a passive subsystem.

CIC servers receive status information from the Status Aggregator server.

Note: In order for Status Aggregator to include status information about a user, that user must have an associated email account matching his or her LDAP (or other data source) email account.

How Status Aggregator Differs from Multi-Site

The features of Status Aggregator overlap somewhat with CIC Multi-Site, an optional software module that links together two or more CIC contact centers. However, the two products serve different purposes and are appropriate in different situations:

- Status Aggregator is designed to provide status information, while Multi-Site is designed to provide user mobility.
- Status Aggregator consolidates status information from users on different CIC servers, while Multi-Site links together CIC servers that all have the same set of users.

The following table compares the features of Status Aggregator to those of Multi-Site.

Feature	Status Aggregator	Multi-Site
Organization-wide directory	Yes	Yes
Universal user extensions (users keep their usual telephone extensions when in remote offices)	No	Yes
Real-time status	Yes	Yes
Scalable. Each Status Aggregator server efficiently handles status information for over 50,000 users and over five CIC servers.	Yes	No
Allows change of status	No	Yes
Server	Status Aggregator server. Must be on stand-alone server.	RTM server. For 200 or fewer users, can be on any CIC server. For more than 200 users, must be on stand-alone server.
Architecture	SA Server + SA clients. Each Status Aggregator server gets information from all connected IC Servers.	RTM server + CIC clients. Each RTM server gets information from the CIC servers that are in its collective. Each CIC server must include the EMSServer subsystem.
Fault tolerance	Two or more Status Aggregator servers can be "fail-over" backups for each other.	No fail-over backup between multiple RTM servers.

For more information about Multi-Site, see *CIC Multi-Site Technical Reference* at <u>https://help.genesys.com/cic/mergedProjects/wh_tr/desktop/multi_site_technical_reference.htm</u>.

How Status Aggregator Works with Different CIC Editions

Status Aggregator must be at the same version level as your CIC server.

How Status Aggregator Uses Security Certificates

Status Aggregator uses security certificates to verify the identities of the Status Aggregator and CIC servers with which it exchanges status data. Using security certificates prevents unauthorized systems or individuals from intercepting or modifying the exchanged status data.

For more information about how Status Aggregator uses certificates, see <u>Generate SSL Security Certificates</u> and <u>3: Import</u> <u>Certificates Into Each CIC Server</u> in this document. For background information about security and certificates, see the *PureConnect Security Features Technical Reference* at <u>https://help.genesys.com/cic/mergedProjects/wh_tr/desktop/security_features.htm</u>.

Installing and Configuring Status Aggregator

This section covers:

- Installing Status Aggregator
- Setting parameters for the Status Aggregator server
- Configuring Status Aggregator data sources and contact list sources
- Importing Status Aggregator security certificates into each CIC server

Installation Pre-Requisites and System Requirements

Installing Status Aggregator requires the following:

- Customer Interaction Center 2015 R1 or later
- Microsoft Active Directory (any version compatible with Interaction Administrator)
- An account (such as local administrator) with permissions to install and run a service.
- A dedicated server for Status Aggregator. System requirements are the same as for a CIC server. For more information, see: https://my.inin.com/products/cic/Pages/Software-Requirements.aspx
- Security permissions to read Active Directory data. In particular, the CIC data source configured in Interaction Administrator must use an account that has read access to the Active Directory server.
- Two-way read access between the Status Aggregator and the CIC servers.
- Files for the AdminGenSSLCerts utility program. Contact Customer Care to obtain this utility. On each CIC server that connects to Status Aggregator, copy the AdminGenSSLCerts utility files to the \I3\IC\Server folder.

Install Status Aggregator

Note: If you want to store log files in a folder other than the default (\Windows\temp\inin_tracing), create the folder before you begin installing Status Aggregator.

The Status Aggregator install is available to install from the CIC .iso file.

To install Status Aggregator:

- 1. If you have not done so already:
 - a. Download the CIC 2015 R1 or later .iso file from the PureConnect Product Information site at <u>https://my.inin.com/products/Pages/Downloads.aspx</u>.
 - b. Copy the .iso file to a file server (non-CIC server) with a high-bandwidth connection to the server(s) on which you will be running the CIC 2015 R1 or later installs.
 - c. Mount the .iso file and share the contents to make them accessible to the server(s) on which you will be running the CIC 2015 R1 or later installs.
- 2. Navigate to the \Installs\Off-ServerComponents directory on the file server.
- 3. Copy the Status Aggregator .msi file, for example, StatusAggregator_2015_R1.msi to the server on which you plan to run this install and double-click to launch it.
- 4. In the Welcome window, click Next.

The program displays the Custom Setup dialog box.

- 5. In the **Custom Setup** dialog box:
 - The Feature Selector icon lets you choose which features of a program to install. For Status Aggregator, ignore this icon because you need to install all the features of the program.
 - The Reset button lets you reset the dialog box's values to their default values.
 - The **Disk Usage** button lets you see how much disk space you have free on the drive where you will install Status Aggregator.
- 6. Click Next.

The program displays the Domain User Validation dialog box.

In this dialog box, the setup wizard typically fills in the **User** and **Domain** text boxes with your Windows login information. Usually, you only need to fill in your password.

- 7. In the **Domain User Validation** dialog box, type any required information in the text boxes, then click **Next**. The program displays the **Status Aggregator Servers** dialog box.
- 8. Click Next.

The program displays the Ready to Install Status Aggregator dialog box.

9. Click Install.

The program displays a progress bar while it installs Status Aggregator. When installation is complete, it displays the **Completed** message.

By default, the PureConnect QoS driver will be silently installed and the certificate will be added to the **Trusted Publishers** list. If your site has reasons to modify this default behavior, see KB article Q131006915300479 and follow the instructions provided to modify the QoS properties and run the install using Group Policy or other methods.

Generate SSL Security Certificates

After you click the **Finish** button in the final **Status Aggregator Setup Wizard** dialog box, the installation program displays the **Administrator's Tool for Generating SSL Certificates** dialog box.

Note: For the steps to generate certificates manually by using the GenSSLCertsU command-line utility, see "Generating Certificates Manually with GenSSLCertsU" in the *PureConnect Security Features Technical Reference* at https://help.genesys.com/cic/mergedProjects/wh_tr/desktop/security_features.htm.

🟶 Administrator's Tool For Generating SSL Ce	ertificates 🔀
Select servers to generate Subsystems ce Click the 'Add' button to generate Subsystem	
Generate the subsystems certificate for each serv Root Directory: C:\Documents and Settings\d	
Servers to generate subsystems certificate for:	b C
	Accept Cancel

In this dialog box, you specify the folder where you want to store your SSL security certificates. You then create a list of servers for which the program will generate SSL certificates. Use these controls:

(a) Root Directory box

Here, you enter the path of the folder where the program should store your SSL certificates for all the servers. Under this folder, the program creates a separate subfolder for each server in your list (c).

(b) Servers To Generate Subsystems Certificate For box

Here, you type the name of a server for which you want to generate SSL certificates.

(c) Server list box

Lists all the servers for which it will generate certificates.

(d) Add button

Clicking this button adds the server name in (b) to the list in (c).

(e) Remove button

If you have clicked a server name in box (c) to select it, clicking this button removes that server name from the server list.

To generate SSL security certificates

- 1. Click the Browse button (a) and browse to the folder where you want to store certificates.
- 2. In the Servers box (b), type the name of a server for which to generate certificates.
- Click the Add button (d).
 The program adds the server name in (b) to the server list in (c).
- 4. Repeat steps 2 and 3 for each server that requires SSL certificates.
- 5. Click the Accept button.

The program opens a command window and shows its progress as it creates a subfolder for the first server in the server list and puts certificates in the subfolder. Then, it displays a message telling you to move the subfolder to that server.

6. Click **OK** in the message.

The program displays a command window and message for each server in the list.

7. Copy all the subfolders under the SSL certificates folder, which you entered in the Root Directory box, onto a USB key drive.

You will later import the certificates onto the CIC server in <u>3: Import Certificates Into Each CIC Server</u> later in this document.

Overview of Configuring Status Aggregator

Configuring Status Aggregator has four major steps:

- Step 1: Configure Status Aggregator data sources in Interaction Administrator.
- Step 2: Configure Status Aggregator contact list sources in Interaction Administrator.
- Step 3: Import certificates into each CIC server.
- Step 4: Set parameters for the Status Aggregator server.

1: Configure Status Aggregator Data Sources

The first major step is to configure the Status Aggregator data source in Interaction Administrator on each CIC server. In a multi-CIC server environment, each CIC server should have a data source configuration pointing to the same source. The most common data source is a Lightweight Directory Access Protocol (LDAP) server, but it can be some other data source. This section shows how to configure Status Aggregator for an LDAP data source.

To configure Status Aggregator data sources in Interaction Administrator:

- 1. If needed, start Interaction Administrator.
- 2. Add a new data source:
 - a. In the tree pane on the left, click the IC Data Sources container.
 - b. In the IC data source pane on the right, right-click an empty area.
 - c. In the shortcut menu, click New.

Interaction Administrator displays the Entry Name dialog box.

- d. In the text box, type a name for your enterprise directory and click **OK**. Interaction Administrator displays the **IC Data Source type** dialog box.
- e. In the list box, click **LDAP** and then click the **Next** button. Interaction Administrator displays the configuration dialog.

LDAP I	Data Sourc	e Configura	ation				
Subty	/pe:	Other		-	🔽 Read On	ly	
Cor	nnection Info	rmation					
Hos	t Name:					Port:	
Bind	IDN:					Password:	
Sea	rch DN:						
Additi	ional Informa	ition:					
	Help		ancel	< <u>B</u> ac	k Nex	t >	Einish

- 3. Configure your new data source (Enterprise Directory):
 - a. Expand the Subtype list box and click Active Directory.
 - b. In the Host Name text box, type the domain name of your Active Directory host.
 - c. If your Active Directory server listens on a specific port, type it in the **Port** text box.
 If you leave the **Port** text box blank, the CIC server will use the default port.
 - d. In the **Bind DN** text box, type the distinguished name of the user account that the CIC server will use to connect to the Active Directory server. For example, you might type:

CN=Administrator, CN=Users, DC=domain, DC=com

Note: DN means distinguished name. The **Bind DN** text box contains credentials that let the CIC server log into the Active Directory server.

- e. In the **Password** text box, type the appropriate password.
- f. In the **Search DN** text box, type the distinguished name of the organizational unit to which you want to connect. For example, you might type:
 - OU=AllUsers, DC=domain, DC=com
- g. Leave the Additional Information text box blank.
- h. Click the **Finish** button.

Your new data source is configured.

2: Configure Status Aggregator Contact List Sources

The second major step is to configure contact list sources in Interaction Administrator. Users can open the contact list in their clients. The list gets its information from the data source.

In other words, the name you give this contact list is the name that will appear in the **General Directories** list of pages in the CIC client. Users will select this name.

To configure Status Aggregator contact list sources in Interaction Administrator:

- 1. If needed, start Interaction Administrator.
- 2. Add a new contact list source:
 - a. In the tree pane on the left, click the Contact List Sources container.
 - b. In the contact list source names pane on the right, right-click an empty area.
 - c. In the shortcut menu, click New.
 - Interaction Administrator displays the Entry Name dialog box.
 - d. In the text box, type the name of your enterprise directory and click OK.
 - Interaction Administrator displays the Contact List Source Configuration dialog box.

Contact List Source Confi	iguration - Enterprise Directory ? >
Configuration Options	Multi-Language Support Custom Attributes History
IC Data Source:	Public
Label:	Enterprise Directory 🗖 Has Status
Driver	
Driver: IC	ACT! Contacts
© Java	Class Name;
C COM/DCOM	CLSID;
Additional Information:	
	OK Cancel

- 3. Configure your new contact list data source:
 - a. Expand the IC Data Source list box and click the IC data source that you configured for Status Aggregator.
 - b. If needed, type the name of your contact list in the Label text box.
 - c. Select the Has Status check box.
 - d. In the Driver area, expand the Driver list box and click IC LDAP Contacts.
 - e. If you use an object class other than the IC default object class of **i3person** to store contact information, then in the Additional Information text box, type:

```
ATTRIBUTE_MAPPING_FILE="cpath to attribute file>\attributefile.txt";
NEXT_POLLING_TIME=2008-11-12 12:01:00; POLLING_INTERVAL=86400
```

Note:

These parameters are (1) The path to the attribute mapping file; (2) The next date and time when Status Aggregator should poll this source for information and (3) The time interval that Status Aggregator should wait after each poll before it polls this source again. The **NEXT_POLLING_TIME** parameter is in UTC time (Greenwich Mean Time), five hours later than U.S. Eastern Standard time. The **POLLING_INTERVAL** parameter is in seconds so, for example, 86400 stands for 24 hours.

The attribute mapping file parameter is needed only if you use an object class other than the IC default object class of **i3person** to store contact information. If you create your own custom object class, you must create a text file that maps CIC attributes to the attributes of your object class. Use the file name and path as the attribute mapping file parameter. For more information, see "Using LDAP for Customer Interaction Center Contact Lists" on the PureConnect Customer Care site.

The **NEXT_POLLING_TIME** parameter value should be set as UTC time in ISO 8601 format (YYYY-MM-DD hh:mm:ss). By default, the **NEXT_POLLING_TIME** value gets set to 12a.m. of the night of the install and the **POLLING_INTERVAL** value gets set to 86400.

4. Click OK.

Interaction Administrator adds and configures your new contact list data source.

3: Import Certificates Into Each CIC Server

The third major step is to import certificates into each CIC server. You should follow these steps on each CIC server and peer Status Aggregator server. Only administrator accounts can import certificates. In addition, the files <code>AdminGenSSLU.exe</code> and <code>AdminGenSSLU.dll</code> must be in the same directory on the CIC server.

To import certificates:

- 1. In Windows Explorer, open the \Windows\temp folder on the hard drive from which the computer starts.
- 2. Under the \Windows\temp folder, create a subfolder named Certs.
- 3. From the USB key drive, copy the certificates for this CIC server into the new Certs folder you just created.
- 4. In the Certs folder, double-click ImportSubsystemsCertificate.bat.

The batch file opens a command window and displays its progress as it imports the certificates. When complete, it displays the message "Successfully imported into the Subsystems certificate for ..."

Warning!

If the batch file does not display the "success" message, then it did not import the certificates. Verify that you are using an administrator account. Press the spacebar to close the command window.

The Status Aggregator server and the CIC server are now in a *trusted* relationship and can communicate securely.

4: Set Parameters for the Status Aggregator Server

The fourth major step is to tell each CIC server the name of the Status Aggregator server that will provide aggregated status information from other CIC servers. Until you set this parameter, the CIC servers do not know where to look for aggregated status information.

To set parameters for the Status Aggregator server:

- 1. Start Interaction Administrator.
- 2. Display the Server Parameters container.

<u>File Edit View Context Window He</u>	elp			_ 5
22 1 6 6 2 7 1				
😽 Collective	Parameter Name	e .	/ Value	
	AdminServerMo	nitorPath	\${SERVER}\Parameters\Attendant Audio Path\Value;\${SERV	
Peer Sites	Attendant Audi	o Path	D:\I3\IC\Resources\InteractionAttendantWaves	
I OCI SKOS	Attendant Fax	Path	D:\I3\IC\Resources\InteractionAttendantFaxes	
	Collective Supp	ort	1	
- 🥮 Telephony Resources	CustomMirrorDi	r	+D:\I3\IC\Resources;+D:\I3\IC\HostTools;+D:\I3\IC\Server	
- 🎠 Lines	DID Voicemail W	/orkgroup		
- 🖉 Interfaces	e-FAQ Support		0	
	EnableSupervis	oryRecordAndMonitor	No	
SMDI Ports	External Priority	/ Voicemail	No	
F Stations	Handler Path		D:\I3\IC\Server\Handlers	
Hanaged IP Phones	I3tables Path		D:\I3\IC\Server\I3Tables\	
-	IconPath		Interactive Intelligence	
Audio Sources	InitialMirrorDir			
	Internal Call Cla	ssifications	Intercom, Internal	
	MirrorException	s	*.ivp	
🗄 🌍 Regionalization	NewVMPollingIn	terval	240	
	Play Oueue Anr	nouncements	External	
	Reco Call Type		Both	
	Recording Path		D:\I3\IC\Recordings\	
	RecordServer			
- 🎭 Roles	ReportCompone	entsInstalled	REPORTS: PMOLOGGING	
	ReportFilePath		\\\${SERVERNAME}\IC_Reports\SQL	
	Resource Path		D:\I3\IC\Resources	
+ A Password Policies	Rx Document P	ath	D:\I3\IC\Server\I3RxDocs	
	Server Path		D:\I3\IC	
	ServerReportLo	gDataDestination	PMQ:IC Report Logging	
	SNMPTrapEnter		ININ	
🗄 🥼 Account Codes	StatusAggregat		ge-statusag	
- 🞯 Wrap-up Codes	SwitchAddress		7	
🎲 Client Buttons	SwitchComPort			
		Initial Ping Delay	5	
A Part of the second	SuitchouorSoru		OF DCUICI	

3. Add (or modify, if already present) a parameter named StatusAggregatorServer:

Warning!

The name of this parameter must be StatusAggregatorServer.

4. For the parameter value, enter the host name(s) of the Status Aggregator server(s). Use semicolons to separate names.

Warning!

Do not enter a fully-qualified domain name. Use only the host name.

Interaction Administrator adds the new parameter and gives it the value you entered.

Starting and Running Status Aggregator

This section covers:

- Starting Status Aggregator on each CIC server
- User operation of Status Aggregator

After you have installed and configured Status Aggregator, only two major steps remain:

- On the Status Aggregator server, the administrator starts Status Aggregator or verifies that it is already running.
- In each user's CIC client, each user views status information that Status Aggregator has collected from all its connected CIC servers.

Users access and view consolidated information from Status Aggregator by using the CIC client. In fact, because Status Aggregator runs behind the scenes, users might not even realize that they are viewing non-local status information.


With Status Aggregator running, users access information in the CIC client in the same way as they always have. The only difference is that they now see status information from remote offices and from their local office.

Start Status Aggregator

Status Aggregator starts automatically. Usually, you do not need to do anything to start the program. In case of a problem, however, you might want to verify that Status Aggregator has started and is running.

To start Status Aggregator or to verify that it is running:

1. On the Status Aggregator server, click the Start button (a), point to Administrative Tools (b), and click Services (c).



2. In the Services window, scroll down to for ININ Process Launcher.

+ → 🗊 🗗 🕻	3 🗟 😭 📰 🕨 🗉 🖷	•				
Services (Local)	Services (Local)					
	ININ Process Louncher	Name /	Description	Status	Startup Type	Lo A
		BHuman Interface Device Access	Enables generic inp		Disabled	Lo
	Sco the service	SIMPI CD-Burning COM Service	Manages CD recor		Disabled	Lo
	Exclart the service	Sindexing Service	Indexes contents		beldevi	Los
		BIDIN Process Launcher		Started	Au matic	QE
		SINDN Tracing Initialization	ININ Tracing Initial	Started	Au omatic	Lo
	1	Sinteractive Update Client	Enables the downs	Started	Utomatic	Lo_
		Sintersite Messaging	Enables messages		Disabled	Los
		SPSEC Services	Provides end-to-en	Started	Automatic	Lo
		Serberos Key Distribution Center	On domain controll		Disabled	Los
		SLicense Logging	Monitors and recor		Disabled	No
		Succession Disk. Manager	Detects and monit	Started	Automatic	Los
	1	SLogical Disk Manager Administrative Service	Configures hard d		Manual	Lo
		McAfee Framework Service		Started	Automatic	Lo
		Messenger	Transmits net send		Disabled	Lo
		Set Morosoft Software Shadow Copy Provider	Manages software		Manual	Lo-
	1	Canal Street France	Mondaine & contain	Charlot	A. A. Antonio Mice	1

- 3. In the ININ Process Launcher line, view the value in the Status column:
 - a. If the **Status** column says **Running**, then Status Aggregator is already running and you do not need to do anything more.
 - b. If the Status column does not say Running, double-click the line to start Status Aggregator.

User Operation of Status Aggregator

Strictly speaking, users don't run Status Aggregator at all. When they use the CIC client to look up status information, Status Aggregator runs in the background and supplies consolidated status information through the CIC client. The only difference that users will see is that they can now view status information not only for their local offices, but for any office or unit with a CIC server that feeds information to Status Aggregator.

Add Status Aggregator Directory to the CIC Clients

Once Status Aggregator has been installed and configured on the Status Aggregator server and its associated CIC servers, CIC client users can add directory pages to display all local and remote status data.

To add a new directory view to your version of the CIC client, see the following help topics in the PureConnect Documentation Library:

- Interaction Desktop: <u>Add or Close Views</u> and <u>Working With Directories</u>.
 - Note:
 - In the New View window, search for General Directories.
- Interaction Connect: Add or Close Views and Directories.

The new tab works the same way as the typical CIC client directory tab. Users can search for individual or group statuses by typing values in the text boxes at the top of the columns and can display an individual's status by right-clicking his/her line in the table.

Appendix A: Antivirus Requirements and Best Practices

Genesys has verified that McAfee VirusScan and Symantec AntiVirus software can be installed on the CIC server, other network servers (such as email servers), and workstations, as part of a system-wide antivirus strategy. The customer or partner has the option to install antivirus software. See the PureConnect Testlab site at http://testlab.genesys.com for the latest supported versions of McAfee VirusScan and Symantec AntiVirus.

Please note the following antivirus requirements and best practices:

Run a scan of all disks during off-peak hours once per day, or at least once per week. Synchronize this effort with other backup tasks that are typically run daily.

We highly recommend that active scanning be disabled while running Interaction Media Server installs and while updating the server. Active scanning locks files, causes excessive disk I/O, and high CPU utilization that can result in system slowdowns or failure.

However, if active scanning is a requirement, it should not be turned on during business hours, especially if the server is under a high CPU load.

Apply the following configuration changes to optimize the Interaction Media Server's CPU, disk, and memory usage:

- 1. Update the virus definition files daily.
- 2. Disable scanning files on reading from disk configure the software to scan only when writing to disk.
- 3. Scan default files plus designated additional file types, not all files.
- 4. Exclude the following directories and their subdirectories from active scanning
 - *\${Drive}*\Program Files\Interactive Intelligence\Recordings (or where specified during the installation)
 - The drive/directory specified during installation for PureConnect log files

Note:

Since the Recordings directory is shared on the network, you increase the risk of exposure to virus by excluding this directory from active scanning. However, if you chose to include it in the active scan and there is a high volume of recording activity, scanning may affect the performance of the system and the capacity of call recordings.

- 5. Exclude the following extensions from being scanned:
 - .ivp
 - .dxs
 - .ininlog (IC log file format)
 - .ininlog.ininlog_idx (IC log file format)

Change Log

Date	Changes
08-December-2008	Corrected GMT time.
27-October 27-2009	Corrected description of the StatusAggregatorServer parameter.
12-March-2010	Updated title page, copyright / trademark information, and platform statement.
15-July-2010	Updated installation instructions for SU10 New Patch Target.
23-August-2010	Corrected Figure 2-5 (setup complete).
30-November-2010	Updated information about how to obtain the AdminGenSSLCerts utility.
10-January-2011	Updated index.
25-May-2011	Clarified "Install Status Aggregator." Added explanation of attribute mapping file. Expanded "Configure Status Aggregator Contact List Sources." Updated references to OCS and Lync admin guides.
18-October-2011	Updated for IC 4.0.
11-November-2011	Updated system requirements section and support site link.
21-August-2012	Added back information about support for Lync-OCS.
07-March-2014	Made miscellaneous improvements in explanations of installation and configuration. Updated copyright page.
15-August-2014	Updated documentation to reflect changes required in the transition from version 4.0 SU# to CIC 2015 R1, such as updates to product version numbers, system requirements, installation procedures, references to Product Information site URLs, and copyright and trademark information.
12-January-2015	Made minor corrections in sections "Install Status Aggregator" and at the end of Chapter 2.
09-September-2015	 Updated documentation to reflect the addition of two CIC client applications, Interaction Desktop and Interaction Connect and the removal of Interaction Client .NET Edition. Changed the name of "Verify Interaction Client Page Options" to "Add Status Aggregator Directory to the CIC Clients" and changed contents to reference help for the different client versions. Updated document formatting and changed chapters to sections.
28-April-2017	Updated documentation to reflect the removal of Interaction Client Web Edition.
16-March-2018	Rebranded to Genesys.

Copyright and Trademark Information

Interactive Intelligence, Interactive Intelligence Customer Interaction Center, Interaction Administrator, Interaction Attendant, Interaction Client, Interaction Designer, Interaction Tracker, Interaction Recorder, Interaction Mobile Office, Interaction Center Platform, Interaction Monitor, Interaction Optimizer, and the "Spirograph" logo design are registered trademarks of Genesys Telecommunications Laboratories, Inc. Customer Interaction Center, EIC, Interaction Fax Viewer, Interaction Server, ION, Interaction Voicemail Player, Interactive Update, Interaction Supervisor, Interaction Migrator, and Interaction Screen Recorder are trademarks of Genesys Telecommunications Laboratories, Inc. The foregoing products are ©1997-2018 Genesys Telecommunications Laboratories, Inc. All rights reserved.

Interaction Dialer and Interaction Scripter are registered trademarks of Genesys Telecommunications Laboratories, Inc. The foregoing products are ©2000-2018 Genesys Telecommunications Laboratories, Inc. All rights reserved.

Messaging Interaction Center and MIC are trademarks of Genesys Telecommunications Laboratories, Inc. The foregoing products are ©2001-2018 Genesys Telecommunications Laboratories, Inc. All rights reserved.

Interaction Director is a registered trademark of Genesys Telecommunications Laboratories, Inc. *e-FAQ Knowledge Manager* and Interaction Marquee are trademarks of Genesys Telecommunications Laboratories, Inc. The foregoing products are ©2002-2018 Genesys Telecommunications Laboratories, Inc. All rights reserved.

Interaction Conference is a trademark of Genesys Telecommunications Laboratories, Inc. The foregoing products are ©2004-2018 Genesys Telecommunications Laboratories, Inc. All rights reserved.

Interaction SIP Proxy and Interaction EasyScripter are trademarks of Genesys Telecommunications Laboratories, Inc. The foregoing products are ©2005-2018 Genesys Telecommunications Laboratories, Inc. All rights reserved.

Interaction Gateway is a registered trademark of Genesys Telecommunications Laboratories, Inc. Interaction Media Server is a trademark of Genesys Telecommunications Laboratories, Inc. The foregoing products are ©2006-2018 Genesys Telecommunications Laboratories, Inc. All rights reserved.

Interaction Desktop is a trademark of Genesys Telecommunications Laboratories, Inc. The foregoing products are ©2007-2018 Genesys Telecommunications Laboratories, Inc. All rights reserved.

Interaction Process Automation, Deliberately Innovative, Interaction Feedback, and Interaction SIP Station are registered trademarks of Genesys Telecommunications Laboratories, Inc. The foregoing products are ©2009-2018 Genesys Telecommunications Laboratories, Inc. All rights reserved.

Interaction Analyzer is a registered trademark of Genesys Telecommunications Laboratories, Inc. Interaction Web Portal and IPA are trademarks of Genesys Telecommunications Laboratories, Inc. The foregoing products are ©2010-2018 Genesys Telecommunications Laboratories, Inc. All rights reserved.

Spotability is a trademark of Genesys Telecommunications Laboratories, Inc. ©2011-2018. All rights reserved.

Interaction Edge, CaaS Quick Spin, Interactive Intelligence Marketplace, Interaction SIP Bridge, and Interaction Mobilizer are registered trademarks of Genesys Telecommunications Laboratories, Inc. Interactive Intelligence Communications as a ServiceSM and Interactive Intelligence CaaSSM are trademarks or service marks of Genesys Telecommunications Laboratories, Inc. The foregoing products are ©2012-2018 Genesys Telecommunications Laboratories, Inc. All rights reserved.

Interaction Speech Recognition and Interaction Quality Manager are registered trademarks of Genesys Telecommunications Laboratories, Inc. Bay Bridge Decisions and Interaction Script Builder are trademarks of Genesys Telecommunications Laboratories, Inc. The foregoing products are ©2013-2018 Genesys Telecommunications Laboratories, Inc. All rights reserved.

Interaction Collector is a registered trademark of Genesys Telecommunications Laboratories, Inc. Interaction Decisions is a trademark of Genesys Telecommunications Laboratories, Inc. The foregoing products are ©2013-2018 Genesys Telecommunications Laboratories, Inc. All rights reserved.

Interactive Intelligence Bridge Server and Interaction Connect are trademarks of Genesys Telecommunications Laboratories, Inc. The foregoing products are ©2014-2018 Genesys Telecommunications Laboratories, Inc. All rights reserved.

The veryPDF product is ©2000-2018 veryPDF, Inc. All rights reserved.

This product includes software licensed under the Common Development and Distribution License (6/24/2009). We hereby agree to indemnify the Initial Developer and every Contributor of the software licensed under the Common Development and Distribution License (6/24/2009) for any liability incurred by the Initial Developer or such Contributor as a result of any such terms we offer. The source code for the included software may be found at http://wpflocalization.codeplex.com.

A database is incorporated in this software which is derived from a database licensed from Hexasoft Development Sdn. Bhd. ("HDSB"). All software and technologies used by HDSB are the properties of HDSB or its software suppliers and are protected by Malaysian and international copyright laws. No warranty is provided that the Databases are free of defects, or fit for a particular purpose. HDSB shall not be liable for any damages suffered by the Licensee or any third party resulting from use of the Databases.

Other brand and/or product names referenced in this document are the trademarks or registered trademarks of their respective companies.

DISCLAIMER

GENESYS TELECOMMUNICATIONS LABORATORIES (GENESYS) HAS NO RESPONSIBILITY UNDER WARRANTY, INDEMNIFICATION OR OTHERWISE, FOR MODIFICATION OR CUSTOMIZATION OF ANY GENESYS SOFTWARE BY GENESYS, CUSTOMER OR ANY THIRD PARTY EVEN IF SUCH CUSTOMIZATION AND/OR MODIFICATION IS DONE USING GENESYS TOOLS, TRAINING OR METHODS DOCUMENTED BY GENESYS.

Genesys Telecommunications Laboratories, Inc. 2001 Junipero Serra Boulevard Daly City, CA 94014 Telephone/Fax (844) 274-5992 www.genesys.com